

Gig Performer OSC Reference as of Gig Performer 3.0

MIDI

| | |
|---|---|
| /oscHandle/Midi <int> [<int> [[<int>]] | Send a 1, 2 or 3 byte Midi message |
| /oscHandle/NoteOn <int> <int> <int> | Send a standard noteOn message, Note Number, Velocity, Channel |
| /oscHandle/NoteOff <int> <int> <int> | Send a standard noteOff message, Note Number, Velocity, Channel |
| /oscHandle/Note <int> <int> <int> <int> | Send a standard noteOn message followed by a NoteOff, Note Number, Velocity, Channel, Duration (ms) |
| /oscHandle/CC <int> <int> <int> | Send a standard CC change message, CC Number, CC Value, Channel |
| /oscHandle/PP <int> <int> <int> | Send a polypressure message, Note Number, Amount, Channel |
| /oscHandle/PB <int> <int> | Send a pitchbend message |
| /oscHandle/AT <int> <int> | Send an aftertouch message |
| /oscHandle/PC <int> <int> | Send a program change message |

Widgets

| | |
|-------------------------------|--|
| /oscHandle/SetValue <double> | Set the value of a widget |
| /oscHandle/GetValue | Get the value of a widget |
| oscHandle/SetCaption <string> | Set the caption of a widget to the value of the string |

Plugins

| | |
|------------------------------------|--|
| /oscHandle/SetParam <int> <double> | Set the parameter value at the given index |
| /oscHandle/GetParam <int> | Request the parameter value for the given index |
| /oscHandle/GetParamCount | Request the number of parameters contained in the plugin |
| /oscHandle/SetPreset <int> | Switch a plugin to the specified preset number |

General

| | |
|---|--|
| /RackSpace/SetVariation <int> | Switch to the specified variation number of the current rackspace |
| /GigPerformer/SwitchToRack <int> <string> [<int>] | Switch to specified rack either by its position in the list or by its name |
| /GigPerformer/SwitchToProgramNumber <int> | Switch to a specific variation (and therefore rackspace) based on the program number |
| /GigPerformer/SwitchToProgramNumber <int> <int> | Send a combined MIDI bank select and program change number (bank select first) |
| /GigPerformer/SwitchToProgramNumber <int> <int> | Sends a MIDI bank select message (with individual MSB and LSB values), followed by a MIDI program change message |
| /GigPerformer/MoveDown | Move to the next variation or rackspace |
| /GigPerformer/MoveUp | Move to the previous variation or previous rackspace |
| /GigPerformer/NextRackSpace | Move to the next rackspace (skips all variations of current rackspace) |
| /GigPerformer/PrevRackSpace | Move to the previous rackspace (skipping variations) |
| /RackSpace/NextVariation | Move to the next variation of the current rackspace |
| /RackSpace/PrevVariation | Move to the previous variation of the current rackspace |
| /Tap | Simulates a "tap" representing a beat for tap tempo detection |
| /SetMasterFader <double> | Set the level of the master fader |
| /SetGlobalTranspose <int> | Set the global transpose value in semitones |
| /GetGlobalTranspose | Request the global transpose |
| /RecordInputs <int> | Start (1) or Stop (0) recording the input channels |

| | |
|---|---|
| <code>/GetRecordStatus</code> | Informs as to whether system is recording (1) or not (0) |
| <code>/SetBPM <double></code> | Set the current BPM |
| <code>/AdjustBPM <double></code> | Increase/decrease current BPM by some amount |
| <code>/GetCurrentBPM</code> | Request the current BPM |
| <code>/Play</code> | Start the playhead |
| <code>/Panic</code> | Stop all MIDI and, by sending it again within 500ms, also reset the audio engine |
| <code>/RackSpace/ListOSCPlugins</code> | Request a list of all plugins that are OSC enabled in the current rackspace |
| <code>/RackSpace/ListOSCWidgets</code> | Request a list of all widgets that are OSC enabled in the current racksace |
| <code>/GigPerformer/ListAllRackspaces</code> | Request a list of all rackspaces |
| <code>/GigPerformer/ListAllVariations [<string>]</code> | Request a list of all variations in the current rackspace or if a rackspace name is provided then the variations for that rackspace |
| <code>/Refresh</code> | Request a status update, useful if your OSC connection is intermittent |
| <code>/TunerView/SetValue <double></code> | Switch to (1.0) or from (0.0) the guitar tuner view |
| <code>/SelectSongByIndex <int> [<int>]</code> | Switch to the song in the current setlist with the specified index, optionally go to specific part number |
| <code>/GigPerformer/SwitchToSong <string> [<int> <string>]</code> | Switch to the song in the current setlist by name, optionally go to specific part number or part name |
| <code>/SelectSongPart <int></code> | Switch to the given song part (0-based indexing) |
| <code>/Song/SwitchToSongPart <string></code> | Switch to the given song part by name |
| <code>/Song/MoveDown</code> | Move to the next item (part or song) in the setlist |
| <code>/Song/MoveUp</code> | Move to the previous item (part or song) in the setlist |
| <code>/GigPerformer/NextSong</code> | Move directly to the next song |
| <code>/GigPerformer/PrevSong</code> | Move directly to the first part of the previous song |
| <code>/Song/NextPart</code> | Move to the next song part of the current song |
| <code>/Song/PrevPart</code> | Move to the previous song part of the current song |
| <code>/GigPerformer/GetSetLists</code> | Get the list of setlists |
| <code>/GigPerformer/SelectSetList <int></code> | Select the given setlist by index (0-based) |
| <code>/SetList/GetSongList</code> | Get the list of songs for the current setlist |
| <code>/SetList/GetSongParts</code> | Get the list of parts for the current song (deprecated) |
| <code>/Song/GetSongParts</code> | Get the list of parts for the current song |
| <code>/SongPart/TakeSnapshot</code> | Takes a snapshot of the current song part |
| <code>/SongPart/ClearSnapshot</code> | Clear the current snapshot |